



DESIGNER DIAMOND™ Technique Project #21 –Specialty Technique Stitches iPhone Case

The pattern given will fit an iPhone or Blackberry. It will work well for most cell phones as well.

Sewing Supplies:

- Clear 1/4" Piecing Foot w/Guide 412927445
- Specialty Candlewick Foot 413162345
- Three Hole Yarn Foot 413187045
- 1/4 yard tone on tone cotton print
- 1/4 yard contrast for lining
- INSPIRA® Tear-A-Way stabilizer
- INSPIRA® Aqua-Magic stabilizer
- Fusible fleece
- 40 wt. Robison Anton rayon embroidery thread
- Bobbin thread
- Sewing thread
- One large bead & one small bead



Cut

From tone on tone print:


One piece 15" x 5"

From fusible fleece:

One piece 15" x 5"

Mark:

On the 15" x 5" tone on tone print, mark a line starting 1/4" from the short end and at a 60° angle as shown.



Mark five additional lines, 1" apart.

1. Following the instructions in the DESIGNER DIAMOND™ Specialty Technique Stitches Technique sheet, stitch the stitches on the six marked rows.
2. To make the fastener, fold a 5" x 4" piece of INSPIRA® Aqua-Magic stabilizer so there are four layers, about 1" wide. Mark a 2" line in the center.

3. Select stitch #16 and begin at the beginning of the line, but let some yarn extend back behind the foot as shown. Stitch on the line, stopping at the end of the line. Trim so there is an inch or so of yarn remaining free. Rinse out the stabilizer and allow to dry. Trim 1/4" from each end of the stitching. Set aside.



4. Place Fusible Fleece on the wrong side of the stitched fabric piece and fuse it in place.

5. Cut 1/4" from the stitched short end, to even up that end. Then cut the fused, stitched piece down to 14" x 3 3/4".

6. Place the template on the unstitched end of the piece and cut it as shown.



7. Using the cut piece, cut a lining piece the same size.

8. On both the lining and the cut piece, mark a bottom fold line 4" from the straight end. Mark a fastener placement line 2 1/2" up from the line as shown on the outer piece.



9. Peel back the fusible fleece from the straight end and trim away 1/4" of the fleece. Fold 1/4" of the fabric to the wrong side and press.

10. Repeat for the lining.

11. Select A2:38. Place the fastener on the marked line and bartack at each end of the stitching to hold it in place.



12. Fold the outer piece on the fold line, right sides together and keeping the 1/4" pressed under, pin.

13. Snap on your Clear 1/4" Piecing Foot w/Guide.

14. Thread with sewing thread top and bobbin.



15. Stitch the side seams.
16. Repeat for the lining.
17. Place the outer and lining pieces right sides together and stitch from the top of the seam, up around the curve across the small straight part and back down the curve to where the seam begins as shown.



18. Trim all seam allowances to 1/8" and clip the corners.
19. Turn through the open top.
20. Hand sew the opening closed, or insert Steam-A-Seam 2 and press with steam to fuse.
21. We sewed a bead on the end of the closure, "just because we could"! Sew through the large bead, then the small bead, and back into the large bead.

